

DYMO Printer Drivers for Windows XP Professional, x64 Edition

Read Me — 16 March 2006

Important: Print a copy of this file before proceeding with the installation.

INTRODUCTION

DYMO is pleased to release 64-bit printer drivers for Windows XP Professional, x64 Edition. These drivers are Beta and as such we ask you to provide us with feedback should you come across any installation or usability issues (please see the section called “**CONTACTING DYMO TECHNICAL SUPPORT**” below for more information).

The drivers included in this installer support the following printer models:

LabelWriter 400
LabelWriter 400 Turbo
LabelWriter Duo
LabelWriter Twin Turbo
LabelWriter 330 (USB connected only)
LabelWriter 330 Turbo (USB connected only)
LabelPoint LP350
LabelManager LM450
LabelManager PCII

These drivers require a third-party application because DYMO Label Software is not currently supported under Windows XP Professional x64. Additionally, the DYMO Label Software SDK is not yet supported under Windows XP Professional x64.

Please note that these drivers are not signed, so you will see a Windows driver signing warning message. You can safely ignore this message.

INSTALLATION

To install these drivers

1. Run the executable called “INSTALL.EXE”.
2. After clicking the ‘Finish’ button, plug the printer into an available USB port and follow the on-screen prompts as follows:

Prompt: *Can Windows connect to Windows Update to search for software?*

Choose: No, not this time

Prompt: *What do you want the wizard to do?*

Choose: Install the software automatically

Prompt: *This software has not passed Windows Logo testing.*

Choose: Continue Anyway

UNINSTALLATION

To remove these drivers

1. Open the Windows Control Panel folder and choose Add/Remove programs. You will find an entry called "Windows Driver Package – DYMO 64-bit Printer Drivers".
2. Select this entry and click the "Change/Remove" button to remove the drivers.

CONTACTING DYMO TECHNICAL SUPPORT

For Technical Support, please visit DYMO on the Internet at: <http://www.dymo.com> or as follows:

In the United States:

Phone #: (203) 588-2500

In Europe:

Phone #: +31/ 020/ 7341 55 29

Fax #:+31/ 020/ 581 9380