DYMO Label v.8.3

Read Me - 15 December 2010

This document contains important information that is not included in any other DYMO Label documentation. It highlights changes in system requirements, new features, and known problems. Please read this document carefully!

NEW IN THIS RELEASE

- · Support for LabelManager 420P and LabelManager PnP printers
- · Support for Microsoft Office 2011
- · Mac Address Book Add-In

SYSTEM REQUIREMENTS

Operating System Support

Mac OS v10.4 and later

INSTALLATION

DYMO Label v.8 requires that you have Mac OS "Administrator" level permissions to install a printer. You MUST be able to modify files in the System folder to install and configure a LabelWriter printer.

NOTE: Do not connect the USB cable to your computer or USB hub until instructed to do so during the software installation. If you have a label printer already installed, disconnect the USB cable from your computer before running the installer and reconnect the cable when instructed to do so.

Manually Installing a Label Printer

Mac OS X v10.5 (all printers)

- 1. Make sure your label printer is plugged in and turned on.
- 2. Open System Preferences for Print & Fax.
- 3. Click the + button under the **Printers** list.
- Select your label printer from the Printer Name list, and then click Add. The printer is added to the Printers list.
- 5. Close the **Printer Preferences** dialog to complete the installation.

Mac OS X v10.4 (printers other than the LabelWriter Duo printer)

If you do not connect the label printer when asked to do so during the software installation or if you have problems with the printer installation, follow these instructions to add the printer manually:

- 1. Make sure your label printer is plugged in and turned on.
- 2. Open System Preferences for Print & Fax.
- 3. Click the + button under the Printers list.
- Select your label printer from the **Printer Name** list, and then click **Add**.
 The printer is added to the Printers list.
- 5. Close the Printer Preferences dialog to complete the installation.

Mac OS X v10.4 (LabelWriter Duo printer)

The LabelWriter Duo printer appears as two separate printers in the Printer Browser: DYMO DUO Tape (or DYMO DUO Tape 128) and DYMO DUO Label. You need to install each of these printers separately.

- 1. Make sure your label printer is plugged in and turned on.
- 2. Open System Preferences for Print & Fax.
- 3. Click the + button under the **Printers** list.

You may see the label printer(s) in the Printer Name list, but the Add button will not be available

- 4. Click More Printers, and then select DYMO DUO USB from the list at the top of the dialog.
- Select DYMO DUO Label from the Printer Name list, and then click Add.
 The printer is added to the Printers list.
- Repeat steps 3 through 5 to add DYMO DUO Tape (or DYMO DUO Tape 128).
 The LabelWriter Duo printer appears as two separate printers in the Printer list: DYMO DUO Tape (or DYMO DUO Tape 128) and DYMO DUO Label.

LabelWriter Duo Notes

- The LabelWriter Duo printer does not support Rendezvous. You will not be able to locate a LabelWriter Duo printer with Rendezvous.
- Printing to both the LabelWriter Duo Tape and Label printers at the same time is not recommended.

NOTE: In some cases, you may not see your printer model listed in the Printer Setup utility or the Add button may be disabled. If this occurs, exit and restart the Printer Setup Utility.

Add-In Support for Microsoft Office

DYMO Label v.8 supports add-ins for Microsoft Word and Excel in Microsoft Office 2004, 2008, and 2010.

Installing DYMO Label Add-Ins

Office 2008

To install and use the add-ins for Office 2008, you must run Word and Excel 2008 at least once BEFORE installing DYMO Label v.8. This allows the Microsoft Office first run processing to create the add-in script folders.

Office 2004

DYMO Label v.8 must be installed on an administrator account for the Office 2004 add-ins to work.

IMPORTANT: DYMO Label v.8 must be installed for each user

DYMO Label v.8 must be installed for each user account that will use the software. For example if you install the software as Administrator and then login to a different account, you must install DYMO Label v.8 on that account.

COMPATIBILITY

Microsoft Office 2004

To use the DYMO Add-In for Microsoft Office 2004, you must have Microsoft Office Service Pack 1 installed. If you do not have Service Pack 1 installed, you will not be able to see the Add-in button in the Word toolbar. You can download the latest Service Pack for Microsoft Office, free of charge, from the Microsoft Web site. If you do not have Service Pack 1 or later installed, you will see the message "An unexpected error occurred while trying to load the Microsoft Framework library."

Printer Support

DYMO Label v.8 supports the following printer models:

LabelWriter 450
LabelWriter 450 Turbo
LabelWriter 450 Twin Turbo
LabelWriter 450 Duo
LabelWriter 4XL
LabelWriter SE450
LabelWriter 400
LabelWriter 400 Turbo
LabelWriter Duo
LabelWriter Twin Turbo

LabelWriter 310 (models 90966, 93029 & 93034 ONLY)

LabelWriter 315 (model 90975 ONLY)

LabelWriter 320 (models 90892, 93031 & 93036 **ONLY**) LabelWriter 330 (model 90891 & 93037 USB **ONLY**)

LabelWriter 330 Turbo (models 90884, 93033 & 93038, USB ONLY)

LabelManager PCII LabelManager 420P LabelManager PnP LabelManager 450 LabelManager 450D LabelPoint 350

Earlier LabelWriter printer models are **NOT** supported by this version of DYMO Label software. In addition, the printers in the list above are only supported when connected through a USB port on your Macintosh computer.

FOR DYMO LABEL SOFTWARE VERSION 7 USERS

Importing DYMO Label Software version 7 Settings

DYMO Label v.8 has a First Run wizard that can import your Version 7 preferences and Address Book. Your Label File Folder settings are imported as a part of this process. When you open label

files in DYMO Label v.8, the File Open dialog points to your default Version 7 label files folder.

DLS 7 Label File Compatibility

DYMO Label v.8 can import Version 7 (.lwl) labels. DYMO Label v.8 cannot open Version tape label (.D1L) files.

CONTACTING DYMO TECHNICAL SUPPORT

For Technical Support, please visit the Support section of the DYMO Web site at:

http://www.dymo.com